


VPN -> Wireguard

Contents

- 1 How it works
- 2 What is a QR Code?
- 3 Install and Setup Guides
- 4 Setup Instructions
 - ◆ 4.1 Note for Access Point mode
 - ◆ 4.2 Android/iOS config import
 - ◆ 4.3 Linux config import
 - ◆ 4.4 Windows config import
 - ◆ 4.5 Options
- 5 Troubleshooting
 - ◆ 5.1 Useful console commands
 - ◆ 5.2 Dynamic WAN IP on router
 - ◆ 5.3 Adding a second peer breaks the first
 - ◆ 5.4 Resolving local hostnames in the tunnel
- 6 Reference




Why WireGuard?

WireGuard® is an extremely simple yet fast and modern VPN that utilizes state-of-the-art cryptography. It aims to be faster, simpler, leaner, and more useful than IPsec, while avoiding the massive headache. It intends to be considerably more performant than OpenVPN.




Instructions

Wireguard




Instructions




Instructions


Wireguard




Instructions



Instructions



Instructions



Instructions

Some key points about Wireguard:

Wireguard

- Layer 3 only - no bridging
- UDP only
- SSH authenticated keys
- Executes in-kernel (and is upstream since Linux 5.6)
- Static routing

How it works

[Quick Start](#), [Conceptual Overview](#)

This tutorial shows the basics of securely creating a tunnel from a client device to DD-WRT. Before proceeding, verify a working reset button and configuration backup in case of problems.

What is a QR Code?

The "Quick Response" Code is a two-dimensional barcode with larger encoded data capacity and high fault tolerance. Since build 38581 in February 2019, a client config can be imported using a QR Code. The advantage of this approach is that there is no need to transfer sensitive information via potentially compromised data channels.

Install and Setup Guides

The WireGuard [installation/downloads](#) page has software and instructions per OS.

[WireGuard Forum Guides](#):

[Server setup](#) [Client setup](#) [Advanced setup](#)

These forum guides have the latest updated information and additional scripts such as:

- Setup DDWRT router as a Wireguard server
- Client devices setup
- Setup DDWRT router as a Wireguard client
- Policy Based Routing for Wireguard
- Wireguard PBR Kill Script
- Info regarding changes for CVE-2019-14899 ([ticket 6928](#))

Setup Instructions

Create the Wireguard tunnel:

DD-WRT *Basic* -> *Tunnels* tab: enable the *Tunnel* then select *WireGuard* for *Protocol Type*.

- *Generate Key* and enter the *oet1* interface IP: **must be a network outside the local LAN range**
- E.g. if the router LAN IP is 192.168.2.1, for the *oet1* IP address use 10.10.0.1.

Wireguard

Add Peers:

For simple configurations, just enter Peer Tunnel IP within the oet1 interface ip range (e.g. 10.10.0.2) and Peer Tunnel DNS (8.8.8.8). Peer Tunnel MTU will be calculated automatically (WAN mtu-40) but can then be edited. Click *Save* then the *QR-Code* button to generate it.

Masquerade the tunnel:

Wireguard must be unbridged, using Forwarding and NAT. Go to *Networking*, unbridge the oet1 interface (automatic since r42067), and enable Masquerade / NAT to have internet on the tunnel. Click *Apply*.

Note for Access Point mode

Add the following firewall rule under Administration/Commands and save as firewall then reboot:

```
iptables -t nat -I POSTROUTING -o br0 -j SNAT --to $(nvram get lan_ipaddr)
```

Android/iOS config import

Android: [Google Play Store](#), iOS: [Apple Store \(12.0 or later\)](#)

WireGuard app: press "+" in the lower right corner, select "Create from QR code", scan from DD-WRT peer, then the app will prompt to name the tunnel. Public IP can be checked [here](#).

Linux config import

Review the Wireguard install page, distribution wiki (e.g. for [Arch](#)) and/or forums for more details.

- Manager: systemd-networkd 237, networkmanager 1.16, connman 1.38
- Graphical QR Code decoder e.g. [qtqr](#)
- Screenshot tool e.g. [flameshot](#)

Using a network manager with Wireguard and preshared key support is optional but much easier.

- Go to *Tunnels* to generate then capture and save a QR Code screenshot
- Open the QR Code decoder and add the png file to decode
- You will be prompted with a decoded textual config file
- Use it to populate wireguard client config in the network manager

Windows config import

Windows Wireguard client: [Windows .msi installer](#)

Graphical QRCode decoder e.g. [CodeTwo QR Code Reader](#)

Options

Persistent Keep Alive: This is seconds between keep alive messages, and is optional. Default is 0 (Disabled). The recommended value for NAT'd devices is 25 seconds.

Wireguard

Allowed IPs: This is required and represents IP addresses that this peer is allowed to use inside the tunnel. Usually the peer's tunnel IP addresses and the networks the peer routes through tunnel. Outgoing packets will be sent to the peer whose *Allowed IPs* contain the destination address, and for multiple matches, the longest matching prefix is chosen. Incoming packets are only accepted if traffic to their source IP would be sent to the same peer. May be specified multiple times.

Preshared Key: A base64 preshared key generated by `wg genpsk`. This is optional and may be omitted. This adds an additional layer of symmetric-key cryptography into the existing public-key cryptography, for post-quantum resistance.

Troubleshooting

If you find any bugs report to: team@wireguard.com

- Start with rebooting all Peers
- Enable `syslogd` at `Services/Services/Sytem Log`
- In the script enable `DEBUG` by uncommenting the line:

```
#DEBUG= # uncomment/comment to enable/disable debug mode
```

Useful console commands

Check the tunnel status:

```
# wg

interface: oet1
  public key: blablaPyAN3eOyINB5JKNu4mHyKwrg3Mblabla=
  private key: (hidden)
  listening port: 51820

peer: BLABLAT3TQJwIE0OYx2qeZWYystRb9BLABLABla=
  endpoint: 212.200.181.116:9208
  allowed ips: 0.0.0.0/0
  latest handshake: 7 seconds ago
  transfer: 14.11 KiB received, 39.85 KiB sent
```

Check if the `oet1` network is NAT'd:

```
# iptables -t nat -v -n -L

Chain POSTROUTING (policy ACCEPT 75 packets, 5466 bytes)
  pkts bytes target     prot opt in     out     source          destination
   71 14687 SNAT       0    --  *       ppp0    192.168.2.0/24  0.0.0.0/0      to:your_r
   38  2381 SNAT       0    --  *       ppp0    10.0.0.0/24    0.0.0.0/0      to:your_r

wg showconf oet1

ip addr

ip route show
```

Wireguard

- More: *ifconfig*, *traceroute*, and *ping*

Dynamic WAN IP on router

After importing configs from DD-WRT to Android/iOS app, edit the *Endpoint* in the *Peer* section e.g.:

- my.ddns.address.com:51820

Adding a second peer breaks the first

Allowed IPs of 0.0.0.0/0 cannot be used for both peers as it causes a collision. Instead set separate peer IPs e.g. 10.10.0.2/32 and 10.10.0.3/32. The Allowed IP's feature is for crypto routing. The key is valid for the entire allowed IP space.

Resolving local hostnames in the tunnel

DD-WRT GUI *Services* -> *DNSMasq* section: enable "Local DNS" and disable "No DNS Rebind", go to *Tunnels* to enter local DNS IP (e.g. 192.168.1.1) for Peer Tunnel DNS (repeat for every peer). Since Wireguard cannot be bridged, the wireguard interface or it's local IP needs specified in dnsmasq as an additional binding interface / listener (interface=oet1). There is also an nvram parameter "dnsmasq_addif" to specify custom additional interfaces (*nvram set dnsmasq_addif=oet1*).

- The easiest way is to simply add a DHCP interface at *Setup* -> *Networking* since the client is not requesting any IP, nothing special will happen. DHCP is present and reachable, but unused.

Reference

DD-WRT source: [Wireguard changesets](#)

DD-WRT forum: [Wireguard](#)

[Wireguard Git Repository](#)

[WireGuard Mailing Lists](#)

[Wireguard DD-WRT setup \(by wuruxu on Github\)](#)